# How to Install Active Directory in Windows Server: A Step-by-Step Guide

## Introduction

Active Directory (AD) is a critical component of Windows Server that enables centralized management of users, devices, and policies. This guide provides a detailed, step-by-step process to install and configure **Active Directory Domain Services (AD DS)** on Windows Server.

# **Prerequisites**


Before proceeding, ensure the following:


- You have a Windows Server (2016/2019/2022) installed and configured.
- The server has a **static IP address** assigned.
- The server has a strong administrator password set.
- You have administrative privileges to install roles and features.

# **Step-by-Step Installation Guide**

#### **Step 1: Open Server Manager**


- 1. Log in to the Windows Server.
- 2. Open **Server Manager** from the taskbar or Start menu.
- 3. Click Manage (top-right corner) and select Add Roles and Features.
- 4. Click **Next** to proceed.






## **Step 2: Select Installation Type**

- 1. Choose Role-based or feature-based installation.
- 2. Click Next.




#### **Step 3: Select Destination Server**

- 1. Select your server from the **server pool**.
- 2. Click Next.




#### **Step 4: Install Active Directory Domain Services (AD DS)**


- 1. In the **Select server roles** screen, check the box for **Active Directory Domain Services**.
- 2. A pop-up window will appear. Click **Add Features** to install necessary dependencies.
- 3. Click Next.



#### **Step 5: Add Required Features**


- 1. Review the additional features required for AD DS.
- 2. Ensure all necessary features are selected.
- 3. Click Next.






**Step 6: Review AD DS Overview** 

- 1. Read the summary of **Active Directory Domain Services** features.
- 2. Click Next.




#### **Step 7: Confirm and Install**

- 1. Review your selections.
- 2. Check **Restart the destination server automatically if required** (optional but recommended).
- 3. Click Install.




#### **Step 8: Promote Server to a Domain Controller**

1. Once the installation completes, click **Promote this server to a domain controller** (available in Server Manager notifications).




## **Step 9: Configure Deployment**

- 1. Choose Add a new forest.
- 2. Enter your desired Root domain name (e.g., example.com).
- 3. Click Next.




#### **Step 10: Configure Domain Controller Options**

- 1. Select the **Forest Functional Level** and **Domain Functional Level** (default settings are fine unless otherwise required).
- 2. Ensure **Domain Name System (DNS) server** is checked.
- 3. Enter a **Directory Services Restore Mode (DSRM) password** (used for AD recovery operations).
- 4. Click Next.




## **Step 11: Configure DNS Options**

1. If prompted about a DNS delegation warning, click **Next** (this is normal if no existing DNS infrastructure exists).



**Step 12: Configure NetBIOS Name** 

- 1. Review the suggested **NetBIOS domain name**.
- 2. Click Next.



#### Step 13: Configure Database, Log, and SYSVOL Paths


1. Leave the default paths for:

o Database folder (C:\Windows\NTDS)

o Log files folder (C:\Windows\NTDS)


o **SYSVOL folder** (C:\Windows\SYSVOL)

2. Click Next.



## **Step 14: Review Configuration**

1. Review the settings summary and Click **Next**.




#### **Step 15: Perform Prerequisites Check**

- 1. Wait for the system to verify prerequisites.
- 2. If warnings appear, review them (most can be ignored, but critical errors must be resolved).
- 3. Click Install.

#### **Step 16: Complete Installation & Restart**

- 1. Once installation is complete, the server will automatically restart.
- 2. After restarting, log in using the **domain administrator account**.
- 3. Open Server Manager → Click Tools → Select Active Directory Users and Computers to verify AD installation.



# **Conclusion**

By following these steps, you have successfully installed and configured **Active Directory Domain Services (AD DS)** on your Windows Server. You can now manage users, groups, and security policies within your domain.

# **Next Steps**

- Configure **Group Policies** (**GPO**) for security and user management.
- Set up **additional Domain Controllers** for redundancy.
- Integrate **DNS** and **DHCP** services for network efficiency.
- Regularly back up Active Directory to prevent data loss.